

ED II: Lecture 2

EM waves: propagation, decay, energy content

Amol Dighe

August 19, 2018

- 1 Relaxation to a stationary state
- 2 Electromagnetic waves
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

- 1 Relaxation to a stationary state
- 2 Electromagnetic waves
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

Stationary and non-stationary states

- Stationary state, by definition, means that the currents are steady and there is no net charge movement, i.e.

$$\nabla \cdot \vec{\mathbf{J}}_s = 0 \quad \text{or} \quad \frac{\partial \rho}{\partial t} = 0 \quad (1)$$

These statements are equivalent, due to continuity.

- If the initial distribution of charges and currents does not satisfy the above criteria, they will redistribute themselves so that a stationary state is reached.
- This process of “relaxation” happens over a time scale that is characteristic of the medium, called the relaxation time.

Stationary and non-stationary states

- Stationary state, by definition, means that the currents are steady and there is no net charge movement, i.e.

$$\nabla \cdot \vec{\mathbf{J}}_s = 0 \quad \text{or} \quad \frac{\partial \rho}{\partial t} = 0 \quad (1)$$

These statements are equivalent, due to continuity.

- If the initial distribution of charges and currents does not satisfy the above criteria, they will redistribute themselves so that a stationary state is reached.
- This process of “relaxation” happens over a time scale that is characteristic of the medium, called the relaxation time.

Stationary and non-stationary states

- Stationary state, by definition, means that the currents are steady and there is no net charge movement, i.e.

$$\nabla \cdot \vec{\mathbf{J}}_s = 0 \quad \text{or} \quad \frac{\partial \rho}{\partial t} = 0 \quad (1)$$

These statements are equivalent, due to continuity.

- If the initial distribution of charges and currents does not satisfy the above criteria, they will redistribute themselves so that a stationary state is reached.
- This process of “relaxation” happens over a time scale that is characteristic of the medium, called the relaxation time.

Relaxation time

- The continuity equation, combining with $\nabla \cdot \vec{\mathbf{D}} = \rho$, gives

$$\nabla \cdot \frac{\partial \vec{\mathbf{D}}}{\partial t} = -\nabla \cdot \vec{\mathbf{J}} \quad (2)$$

- Using $\vec{\mathbf{D}} = \epsilon \vec{\mathbf{E}}$ and $\vec{\mathbf{J}} = \sigma \vec{\mathbf{E}}$,

$$\nabla \cdot \left(1 + \frac{\epsilon}{\sigma} \frac{\partial}{\partial t} \right) \vec{\mathbf{J}} = 0 \quad (3)$$

- The solution to this differential equation is

$$\vec{\mathbf{J}} = \vec{\mathbf{J}}_s + (\vec{\mathbf{J}}_0 - \vec{\mathbf{J}}_s) e^{-t/\tau} \quad (4)$$

where J_0 is the initial current distribution

- $\tau = \epsilon/\sigma$ is the relaxation time
- $\frac{\partial \rho}{\partial t} = -\nabla \cdot \vec{\mathbf{J}}$, $\vec{\mathbf{E}} = \vec{\mathbf{J}}/\sigma$, etc. relax at the same rate.

Relaxation time

- The continuity equation, combining with $\nabla \cdot \vec{\mathbf{D}} = \rho$, gives

$$\nabla \cdot \frac{\partial \vec{\mathbf{D}}}{\partial t} = -\nabla \cdot \vec{\mathbf{J}} \quad (2)$$

- Using $\vec{\mathbf{D}} = \epsilon \vec{\mathbf{E}}$ and $\vec{\mathbf{J}} = \sigma \vec{\mathbf{E}}$,

$$\nabla \cdot \left(1 + \frac{\epsilon}{\sigma} \frac{\partial}{\partial t} \right) \vec{\mathbf{J}} = 0 \quad (3)$$

- The solution to this differential equation is

$$\vec{\mathbf{J}} = \vec{\mathbf{J}}_s + (\vec{\mathbf{J}}_0 - \vec{\mathbf{J}}_s) e^{-t/\tau} \quad (4)$$

where J_0 is the initial current distribution

- $\tau = \epsilon/\sigma$ is the relaxation time
- $\frac{\partial \rho}{\partial t} = -\nabla \cdot \vec{\mathbf{J}}$, $\vec{\mathbf{E}} = \vec{\mathbf{J}}/\sigma$, etc. relax at the same rate.

Relaxation time

- The continuity equation, combining with $\nabla \cdot \vec{\mathbf{D}} = \rho$, gives

$$\nabla \cdot \frac{\partial \vec{\mathbf{D}}}{\partial t} = -\nabla \cdot \vec{\mathbf{J}} \quad (2)$$

- Using $\vec{\mathbf{D}} = \epsilon \vec{\mathbf{E}}$ and $\vec{\mathbf{J}} = \sigma \vec{\mathbf{E}}$,

$$\nabla \cdot \left(1 + \frac{\epsilon}{\sigma} \frac{\partial}{\partial t} \right) \vec{\mathbf{J}} = 0 \quad (3)$$

- The solution to this differential equation is

$$\vec{\mathbf{J}} = \vec{\mathbf{J}}_s + (\vec{\mathbf{J}}_0 - \vec{\mathbf{J}}_s) e^{-t/\tau} \quad (4)$$

where \mathbf{J}_0 is the initial current distribution

- $\tau = \epsilon/\sigma$ is the relaxation time
- $\frac{\partial \rho}{\partial t} = -\nabla \cdot \vec{\mathbf{J}}$, $\vec{\mathbf{E}} = \vec{\mathbf{J}}/\sigma$, etc. relax at the same rate.

Relaxation time

- The continuity equation, combining with $\nabla \cdot \vec{\mathbf{D}} = \rho$, gives

$$\nabla \cdot \frac{\partial \vec{\mathbf{D}}}{\partial t} = -\nabla \cdot \vec{\mathbf{J}} \quad (2)$$

- Using $\vec{\mathbf{D}} = \epsilon \vec{\mathbf{E}}$ and $\vec{\mathbf{J}} = \sigma \vec{\mathbf{E}}$,

$$\nabla \cdot \left(1 + \frac{\epsilon}{\sigma} \frac{\partial}{\partial t} \right) \vec{\mathbf{J}} = 0 \quad (3)$$

- The solution to this differential equation is

$$\vec{\mathbf{J}} = \vec{\mathbf{J}}_s + (\vec{\mathbf{J}}_0 - \vec{\mathbf{J}}_s) e^{-t/\tau} \quad (4)$$

where \mathbf{J}_0 is the initial current distribution

- $\tau = \epsilon/\sigma$ is the relaxation time
- $\frac{\partial \rho}{\partial t} = -\nabla \cdot \vec{\mathbf{J}}$, $\vec{\mathbf{E}} = \vec{\mathbf{J}}/\sigma$, etc. relax at the same rate.

- 1 Relaxation to a stationary state
- 2 Electromagnetic waves**
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

Time-dependent electric field

- No free charges, no external EMF sources. Maxwell \Rightarrow

$$\nabla \times (\nabla \times \vec{\mathbf{E}}) = -\frac{\partial}{\partial t}(\nabla \times \mu \vec{\mathbf{H}}) \quad (5)$$

$$\nabla(\nabla \cdot \vec{\mathbf{E}}) - \nabla^2 \vec{\mathbf{E}} = -\mu \frac{\partial}{\partial t}(\vec{\mathbf{J}}_{\text{fr}} + \epsilon \frac{\partial \vec{\mathbf{E}}}{\partial t}) \quad (6)$$

- This gives the second order partial differential equation

$$\nabla^2 \vec{\mathbf{E}} - \mu \sigma \frac{\partial \vec{\mathbf{E}}}{\partial t} - \mu \epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} = 0 \quad (7)$$

- Depending on whether the $(\partial^2 \vec{\mathbf{E}} / \partial t^2)$ term dominates or the $(\partial \vec{\mathbf{E}} / \partial t)$ one, we'll get two different extremes of behaviour. The former will lead to a **propagating wave**, the latter will lead to a **diffusion equation**, corresponding to a **decaying wave**.

Time-dependent electric field

- No free charges, no external EMF sources. Maxwell \Rightarrow

$$\nabla \times (\nabla \times \vec{\mathbf{E}}) = -\frac{\partial}{\partial t}(\nabla \times \mu \vec{\mathbf{H}}) \quad (5)$$

$$\nabla(\nabla \cdot \vec{\mathbf{E}}) - \nabla^2 \vec{\mathbf{E}} = -\mu \frac{\partial}{\partial t}(\vec{\mathbf{J}}_{\text{fr}} + \epsilon \frac{\partial \vec{\mathbf{E}}}{\partial t}) \quad (6)$$

- This gives the second order partial differential equation

$$\nabla^2 \vec{\mathbf{E}} - \mu\sigma \frac{\partial \vec{\mathbf{E}}}{\partial t} - \mu\epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} = 0 \quad (7)$$

- Depending on whether the $(\partial^2 \vec{\mathbf{E}} / \partial t^2)$ term dominates or the $(\partial \vec{\mathbf{E}} / \partial t)$ one, we'll get two different extremes of behaviour. The former will lead to a **propagating wave**, the latter will lead to a **diffusion equation**, corresponding to a **decaying wave**.

Time-dependent electric field

- No free charges, no external EMF sources. Maxwell \Rightarrow

$$\nabla \times (\nabla \times \vec{\mathbf{E}}) = -\frac{\partial}{\partial t}(\nabla \times \mu \vec{\mathbf{H}}) \quad (5)$$

$$\nabla(\nabla \cdot \vec{\mathbf{E}}) - \nabla^2 \vec{\mathbf{E}} = -\mu \frac{\partial}{\partial t}(\vec{\mathbf{J}}_{\text{fr}} + \epsilon \frac{\partial \vec{\mathbf{E}}}{\partial t}) \quad (6)$$

- This gives the second order partial differential equation

$$\nabla^2 \vec{\mathbf{E}} - \mu\sigma \frac{\partial \vec{\mathbf{E}}}{\partial t} - \mu\epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} = 0 \quad (7)$$

- Depending on whether the $(\partial^2 \vec{\mathbf{E}} / \partial t^2)$ term dominates or the $(\partial \vec{\mathbf{E}} / \partial t)$ one, we'll get two different extremes of behaviour. The former will lead to a **propagating wave**, the latter will lead to a **diffusion equation**, corresponding to a **decaying wave**.

Looking for solution of the form $\vec{\mathbf{E}}(\vec{\mathbf{x}})e^{-i\omega t}$

- The differential equation becomes

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i\sigma}{\epsilon\omega}\right) \vec{\mathbf{E}} = 0 \quad (8)$$

- There are two time scales here: $1/\omega$ and $\tau = \epsilon/\sigma$

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i}{\tau\omega}\right) \vec{\mathbf{E}} = 0 \quad (9)$$

- When $\tau\omega \gg 1$,

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} = 0 \quad (10)$$

which is a wave propagating with speed $c = 1/\sqrt{\mu\epsilon}$

- When $\tau\omega \ll 1$,

$$\nabla^2 \vec{\mathbf{E}} + \frac{i\omega}{\tau\sigma} \vec{\mathbf{E}} = 0 \quad (11)$$

which is the equation for diffusion. In the context of EM waves, this will lead to a decaying solution.

- we shall explore these behaviours in detail now.

Looking for solution of the form $\vec{\mathbf{E}}(\vec{\mathbf{x}})e^{-i\omega t}$

- The differential equation becomes

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i\sigma}{\epsilon\omega}\right) \vec{\mathbf{E}} = 0 \quad (8)$$

- There are two time scales here: $1/\omega$ and $\tau = \epsilon/\sigma$

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i}{\tau\omega}\right) \vec{\mathbf{E}} = 0 \quad (9)$$

- When $\tau\omega \gg 1$,

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} = 0 \quad (10)$$

which is a wave propagating with speed $c = 1/\sqrt{\mu\epsilon}$

- When $\tau\omega \ll 1$,

$$\nabla^2 \vec{\mathbf{E}} + \frac{i\omega}{\tau\sigma} \vec{\mathbf{E}} = 0 \quad (11)$$

which is the equation for diffusion. In the context of EM waves, this will lead to a decaying solution.

- we shall explore these behaviours in detail now.

Looking for solution of the form $\vec{\mathbf{E}}(\vec{\mathbf{x}})e^{-i\omega t}$

- The differential equation becomes

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i\sigma}{\epsilon\omega}\right) \vec{\mathbf{E}} = 0 \quad (8)$$

- There are two time scales here: $1/\omega$ and $\tau = \epsilon/\sigma$

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i}{\tau\omega}\right) \vec{\mathbf{E}} = 0 \quad (9)$$

- When $\tau\omega \gg 1$,

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} = 0 \quad (10)$$

which is a wave propagating with speed $c = 1/\sqrt{\mu\epsilon}$

- When $\tau\omega \ll 1$,

$$\nabla^2 \vec{\mathbf{E}} + \frac{i\omega}{\tau\sigma} \vec{\mathbf{E}} = 0 \quad (11)$$

which is the equation for diffusion. In the context of EM waves, this will lead to a decaying solution.

- we shall explore these behaviours in detail now.

Looking for solution of the form $\vec{\mathbf{E}}(\vec{\mathbf{x}})e^{-i\omega t}$

- The differential equation becomes

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i\sigma}{\epsilon\omega}\right) \vec{\mathbf{E}} = 0 \quad (8)$$

- There are two time scales here: $1/\omega$ and $\tau = \epsilon/\sigma$

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i}{\tau\omega}\right) \vec{\mathbf{E}} = 0 \quad (9)$$

- When $\tau\omega \gg 1$,

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} = 0 \quad (10)$$

which is a wave propagating with speed $c = 1/\sqrt{\mu\epsilon}$

- When $\tau\omega \ll 1$,

$$\nabla^2 \vec{\mathbf{E}} + \frac{i\omega}{\tau c^2} \vec{\mathbf{E}} = 0 \quad (11)$$

which is the equation for diffusion. In the context of EM waves, this will lead to a decaying solution.

- we shall explore these behaviours in detail now.

Looking for solution of the form $\vec{\mathbf{E}}(\vec{\mathbf{x}})e^{-i\omega t}$

- The differential equation becomes

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i\sigma}{\epsilon\omega}\right) \vec{\mathbf{E}} = 0 \quad (8)$$

- There are two time scales here: $1/\omega$ and $\tau = \epsilon/\sigma$

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \left(1 + \frac{i}{\tau\omega}\right) \vec{\mathbf{E}} = 0 \quad (9)$$

- When $\tau\omega \gg 1$,

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} = 0 \quad (10)$$

which is a wave propagating with speed $c = 1/\sqrt{\mu\epsilon}$

- When $\tau\omega \ll 1$,

$$\nabla^2 \vec{\mathbf{E}} + \frac{i\omega}{\tau C^2} \vec{\mathbf{E}} = 0 \quad (11)$$

which is the equation for diffusion. In the context of EM waves, this will lead to a decaying solution.

- we shall explore these behaviours in detail now.

- 1 Relaxation to a stationary state
- 2 **Electromagnetic waves**
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

Propagating (plane wave) solution for \vec{E}

- $\omega\tau \gg 1 \Rightarrow$ displacement current dominates over conduction current

$$\nabla^2 \vec{E} + \mu\epsilon\omega^2 \vec{E} + i\omega\mu\sigma \vec{E} = 0 \quad (12)$$

- Plane wave: all fields are functions of the distance ζ of a plane from the origin. \hat{n} is the normal to this plane.
- $\nabla \rightarrow \hat{n}(\partial/\partial\zeta)$
- Maxwell's equations in this language: (neglect $\vec{J}_{fr} = \sigma\vec{E}$)

$$\hat{n} \cdot \frac{\partial \vec{D}}{\partial \zeta} = 0, \quad \hat{n} \times \frac{\partial \vec{E}}{\partial \zeta} = -\frac{\partial \vec{B}}{\partial t} \quad (13)$$

$$\hat{n} \cdot \frac{\partial \vec{B}}{\partial \zeta} = 0, \quad \hat{n} \times \frac{\partial \vec{H}}{\partial \zeta} = \frac{\partial \vec{D}}{\partial t} \quad (14)$$

Propagating (plane wave) solution for $\vec{\mathbf{E}}$

- $\omega\tau \gg 1 \Rightarrow$ displacement current dominates over conduction current

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (12)$$

- Plane wave: all fields are functions of the distance ζ of a plane from the origin. $\hat{\mathbf{n}}$ is the normal to this plane.
- $\nabla \rightarrow \hat{\mathbf{n}}(\partial/\partial\zeta)$
- Maxwell's equations in this language: (neglect $\vec{\mathbf{J}}_{\text{fr}} = \sigma\vec{\mathbf{E}}$)

$$\hat{\mathbf{n}} \cdot \frac{\partial \vec{\mathbf{D}}}{\partial \zeta} = 0, \quad \hat{\mathbf{n}} \times \frac{\partial \vec{\mathbf{E}}}{\partial \zeta} = -\frac{\partial \vec{\mathbf{B}}}{\partial t} \quad (13)$$

$$\hat{\mathbf{n}} \cdot \frac{\partial \vec{\mathbf{B}}}{\partial \zeta} = 0, \quad \hat{\mathbf{n}} \times \frac{\partial \vec{\mathbf{H}}}{\partial \zeta} = \frac{\partial \vec{\mathbf{D}}}{\partial t} \quad (14)$$

Propagating (plane wave) solution for \vec{E}

- $\omega\tau \gg 1 \Rightarrow$ displacement current dominates over conduction current

$$\nabla^2 \vec{E} + \mu\epsilon\omega^2 \vec{E} + i\omega\mu\sigma \vec{E} = 0 \quad (12)$$

- Plane wave: all fields are functions of the distance ζ of a plane from the origin. \hat{n} is the normal to this plane.
- $\nabla \rightarrow \hat{n}(\partial/\partial\zeta)$
- Maxwell's equations in this language: (neglect $\vec{J}_{fr} = \sigma\vec{E}$)

$$\hat{n} \cdot \frac{\partial \vec{D}}{\partial \zeta} = 0, \quad \hat{n} \times \frac{\partial \vec{E}}{\partial \zeta} = -\frac{\partial \vec{B}}{\partial t} \quad (13)$$

$$\hat{n} \cdot \frac{\partial \vec{B}}{\partial \zeta} = 0, \quad \hat{n} \times \frac{\partial \vec{H}}{\partial \zeta} = \frac{\partial \vec{D}}{\partial t} \quad (14)$$

Propagating (plane wave) solution for $\vec{\mathbf{E}}$

- $\omega\tau \gg 1 \Rightarrow$ displacement current dominates over conduction current

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (12)$$

- Plane wave: all fields are functions of the distance ζ of a plane from the origin. $\hat{\mathbf{n}}$ is the normal to this plane.
- $\nabla \rightarrow \hat{\mathbf{n}}(\partial/\partial\zeta)$
- Maxwell's equations in this language: (neglect $\vec{\mathbf{J}}_{\text{fr}} = \sigma\vec{\mathbf{E}}$)

$$\hat{\mathbf{n}} \cdot \frac{\partial \vec{\mathbf{D}}}{\partial \zeta} = 0, \quad \hat{\mathbf{n}} \times \frac{\partial \vec{\mathbf{E}}}{\partial \zeta} = -\frac{\partial \vec{\mathbf{B}}}{\partial t} \quad (13)$$

$$\hat{\mathbf{n}} \cdot \frac{\partial \vec{\mathbf{B}}}{\partial \zeta} = 0, \quad \hat{\mathbf{n}} \times \frac{\partial \vec{\mathbf{H}}}{\partial \zeta} = \frac{\partial \vec{\mathbf{D}}}{\partial t} \quad (14)$$

Longitudinal components of \vec{E} and \vec{B}

$\vec{E}_{||}$: longitudinal component of \vec{E}

- $(\partial\vec{D}/\partial\zeta)$ equation and dot product of \hat{n} with the $(\partial\vec{H}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{D}\cdot\hat{n}}{\partial\zeta} = 0, \quad \frac{\partial\vec{D}\cdot\hat{n}}{\partial t} = 0 \quad (15)$$

- $\vec{D}_{||}$ is a constant. (in vacuum, $\vec{E}_{||}$ is a constant.)

Longitudinal component of \vec{B}

- $(\partial\vec{B}/\partial\zeta)$ equation and dot product of \hat{n} with the $(\partial\vec{E}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{B}\cdot\hat{n}}{\partial\zeta} = 0, \quad \frac{\partial\vec{B}\cdot\hat{n}}{\partial t} = 0 \quad (16)$$

- $\vec{B}_{||}$ is constant

Longitudinal components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

$\vec{\mathbf{E}}_{\parallel}$: longitudinal component of $\vec{\mathbf{E}}$

- $(\partial\vec{\mathbf{D}}/\partial\zeta)$ equation and dot product of $\hat{\mathbf{n}}$ with the $(\partial\vec{\mathbf{H}}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{\mathbf{D}} \cdot \hat{\mathbf{n}}}{\partial\zeta} = 0, \quad \frac{\partial\vec{\mathbf{D}} \cdot \hat{\mathbf{n}}}{\partial t} = 0 \quad (15)$$

- $\vec{\mathbf{D}}_{\parallel}$ is a constant. (in vacuum, $\vec{\mathbf{E}}_{\parallel}$ is a constant.)

Longitudinal component of $\vec{\mathbf{B}}$

- $(\partial\vec{\mathbf{B}}/\partial\zeta)$ equation and dot product of $\hat{\mathbf{n}}$ with the $(\partial\vec{\mathbf{E}}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{\mathbf{B}} \cdot \hat{\mathbf{n}}}{\partial\zeta} = 0, \quad \frac{\partial\vec{\mathbf{B}} \cdot \hat{\mathbf{n}}}{\partial t} = 0 \quad (16)$$

- $\vec{\mathbf{B}}_{\parallel}$ is constant

Longitudinal components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

$\vec{\mathbf{E}}_{\parallel}$: longitudinal component of $\vec{\mathbf{E}}$

- $(\partial\vec{\mathbf{D}}/\partial\zeta)$ equation and dot product of $\hat{\mathbf{n}}$ with the $(\partial\vec{\mathbf{H}}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{\mathbf{D}} \cdot \hat{\mathbf{n}}}{\partial\zeta} = 0, \quad \frac{\partial\vec{\mathbf{D}} \cdot \hat{\mathbf{n}}}{\partial t} = 0 \quad (15)$$

- $\vec{\mathbf{D}}_{\parallel}$ is a constant. (in vacuum, $\vec{\mathbf{E}}_{\parallel}$ is a constant.)

Longitudinal component of $\vec{\mathbf{B}}$

- $(\partial\vec{\mathbf{B}}/\partial\zeta)$ equation and dot product of $\hat{\mathbf{n}}$ with the $(\partial\vec{\mathbf{E}}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{\mathbf{B}} \cdot \hat{\mathbf{n}}}{\partial\zeta} = 0, \quad \frac{\partial\vec{\mathbf{B}} \cdot \hat{\mathbf{n}}}{\partial t} = 0 \quad (16)$$

- $\vec{\mathbf{B}}_{\parallel}$ is constant

Longitudinal components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

$\vec{\mathbf{E}}_{\parallel}$: longitudinal component of $\vec{\mathbf{E}}$

- $(\partial\vec{\mathbf{D}}/\partial\zeta)$ equation and dot product of $\hat{\mathbf{n}}$ with the $(\partial\vec{\mathbf{H}}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{\mathbf{D}} \cdot \hat{\mathbf{n}}}{\partial\zeta} = 0, \quad \frac{\partial\vec{\mathbf{D}} \cdot \hat{\mathbf{n}}}{\partial t} = 0 \quad (15)$$

- $\vec{\mathbf{D}}_{\parallel}$ is a constant. (in vacuum, $\vec{\mathbf{E}}_{\parallel}$ is a constant.)

Longitudinal component of $\vec{\mathbf{B}}$

- $(\partial\vec{\mathbf{B}}/\partial\zeta)$ equation and dot product of $\hat{\mathbf{n}}$ with the $(\partial\vec{\mathbf{E}}/\partial\zeta)$ equation \Rightarrow

$$\frac{\partial\vec{\mathbf{B}} \cdot \hat{\mathbf{n}}}{\partial\zeta} = 0, \quad \frac{\partial\vec{\mathbf{B}} \cdot \hat{\mathbf{n}}}{\partial t} = 0 \quad (16)$$

- $\vec{\mathbf{B}}_{\parallel}$ is constant

Transverse components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

- Combining the two $\hat{\mathbf{n}} \times$ equations:

$$\hat{\mathbf{n}} \times \left(\frac{\partial^2 \vec{\mathbf{E}}}{\partial \zeta^2} - \mu\epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} \right) = 0 \quad (17)$$

- Differential equation for $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}} \times \hat{\mathbf{n}}$
- General solution: $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} [f(\zeta - ut) + g(\zeta + ut)]$
- If $\vec{\mathbf{E}}_{\perp}$ is sinusoidal:

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{-i(\omega t \pm k\zeta)} \quad (18)$$

- Direction of propagation $\vec{\mathbf{k}} \Rightarrow$

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)} \quad (19)$$

- Using $\hat{\mathbf{n}} \times (\partial \vec{\mathbf{E}}_{\perp} / \partial \zeta) = -\partial \vec{\mathbf{B}}_{\perp} / \partial t$,

$$i\vec{\mathbf{k}} \times \vec{\mathbf{E}}_{\perp} = i\omega \vec{\mathbf{B}}_{\perp} \Rightarrow \vec{\mathbf{B}}_{\perp} = \frac{\vec{\mathbf{k}}}{\omega} \times \vec{\mathbf{E}} \quad (20)$$

Transverse components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

- Combining the two $\hat{\mathbf{n}} \times$ equations:

$$\hat{\mathbf{n}} \times \left(\frac{\partial^2 \vec{\mathbf{E}}}{\partial \zeta^2} - \mu \epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} \right) = 0 \quad (17)$$

- Differential equation for $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}} \times \hat{\mathbf{n}}$

- General solution: $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} [f(\zeta - ut) + g(\zeta + ut)]$

- If $\vec{\mathbf{E}}_{\perp}$ is sinusoidal:

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{-i(\omega t \pm k \zeta)} \quad (18)$$

- Direction of propagation $\vec{\mathbf{k}} \Rightarrow$

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)} \quad (19)$$

- Using $\hat{\mathbf{n}} \times (\partial \vec{\mathbf{E}}_{\perp} / \partial \zeta) = -\partial \vec{\mathbf{B}}_{\perp} / \partial t$,

$$i \vec{\mathbf{k}} \times \vec{\mathbf{E}}_{\perp} = i \omega \vec{\mathbf{B}}_{\perp} \Rightarrow \vec{\mathbf{B}}_{\perp} = \frac{\vec{\mathbf{k}}}{\omega} \times \vec{\mathbf{E}} \quad (20)$$

Transverse components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

- Combining the two $\hat{\mathbf{n}} \times$ equations:

$$\hat{\mathbf{n}} \times \left(\frac{\partial^2 \vec{\mathbf{E}}}{\partial \zeta^2} - \mu\epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} \right) = 0 \quad (17)$$

- Differential equation for $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}} \times \hat{\mathbf{n}}$
- General solution: $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} [f(\zeta - ut) + g(\zeta + ut)]$
- If $\vec{\mathbf{E}}_{\perp}$ is sinusoidal:

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{-i(\omega t \pm k\zeta)} \quad (18)$$

- Direction of propagation $\vec{\mathbf{k}} \Rightarrow$

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)} \quad (19)$$

- Using $\hat{\mathbf{n}} \times (\partial \vec{\mathbf{E}}_{\perp} / \partial \zeta) = -\partial \vec{\mathbf{B}}_{\perp} / \partial t$,

$$i\vec{\mathbf{k}} \times \vec{\mathbf{E}}_{\perp} = i\omega \vec{\mathbf{B}}_{\perp} \Rightarrow \vec{\mathbf{B}}_{\perp} = \frac{\vec{\mathbf{k}}}{\omega} \times \vec{\mathbf{E}} \quad (20)$$

Transverse components of \vec{E} and \vec{B}

- Combining the two $\hat{n} \times$ equations:

$$\hat{n} \times \left(\frac{\partial^2 \vec{E}}{\partial \zeta^2} - \mu\epsilon \frac{\partial^2 \vec{E}}{\partial t^2} \right) = 0 \quad (17)$$

- Differential equation for $\vec{E}_\perp = \vec{E} \times \hat{n}$
- General solution: $\vec{E}_\perp = \vec{E}_{\perp,0} [f(\zeta - ut) + g(\zeta + ut)]$
- If \vec{E}_\perp is sinusoidal:

$$\vec{E}_\perp = \vec{E}_{\perp,0} e^{-i(\omega t \pm k\zeta)} \quad (18)$$

- Direction of propagation $\vec{k} \Rightarrow$

$$\vec{E}_\perp = \vec{E}_{\perp,0} e^{i(\vec{k} \cdot \vec{r} - \omega t)} \quad (19)$$

- Using $\hat{n} \times (\partial \vec{E}_\perp / \partial \zeta) = -\partial \vec{B}_\perp / \partial t$,

$$i\vec{k} \times \vec{E}_\perp = i\omega \vec{B}_\perp \Rightarrow \vec{B}_\perp = \frac{\vec{k}}{\omega} \times \vec{E} \quad (20)$$

Transverse components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

- Combining the two $\hat{\mathbf{n}} \times$ equations:

$$\hat{\mathbf{n}} \times \left(\frac{\partial^2 \vec{\mathbf{E}}}{\partial \zeta^2} - \mu\epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} \right) = 0 \quad (17)$$

- Differential equation for $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}} \times \hat{\mathbf{n}}$
- General solution: $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} [f(\zeta - ut) + g(\zeta + ut)]$
- If $\vec{\mathbf{E}}_{\perp}$ is sinusoidal:

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{-i(\omega t \pm k\zeta)} \quad (18)$$

- Direction of propagation $\vec{\mathbf{k}} \Rightarrow$

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)} \quad (19)$$

- Using $\hat{\mathbf{n}} \times (\partial \vec{\mathbf{E}}_{\perp} / \partial \zeta) = -\partial \vec{\mathbf{B}}_{\perp} / \partial t$,

$$i\vec{\mathbf{k}} \times \vec{\mathbf{E}}_{\perp} = i\omega \vec{\mathbf{B}}_{\perp} \Rightarrow \vec{\mathbf{B}}_{\perp} = \frac{\vec{\mathbf{k}}}{\omega} \times \vec{\mathbf{E}} \quad (20)$$

Transverse components of $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$

- Combining the two $\hat{\mathbf{n}} \times$ equations:

$$\hat{\mathbf{n}} \times \left(\frac{\partial^2 \vec{\mathbf{E}}}{\partial \zeta^2} - \mu\epsilon \frac{\partial^2 \vec{\mathbf{E}}}{\partial t^2} \right) = 0 \quad (17)$$

- Differential equation for $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}} \times \hat{\mathbf{n}}$
- General solution: $\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} [f(\zeta - ut) + g(\zeta + ut)]$
- If $\vec{\mathbf{E}}_{\perp}$ is sinusoidal:

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{-i(\omega t \pm k\zeta)} \quad (18)$$

- Direction of propagation $\vec{\mathbf{k}} \Rightarrow$

$$\vec{\mathbf{E}}_{\perp} = \vec{\mathbf{E}}_{\perp,0} e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)} \quad (19)$$

- Using $\hat{\mathbf{n}} \times (\partial \vec{\mathbf{E}}_{\perp} / \partial \zeta) = -\partial \vec{\mathbf{B}}_{\perp} / \partial t$,

$$i\vec{\mathbf{k}} \times \vec{\mathbf{E}}_{\perp} = i\omega \vec{\mathbf{B}}_{\perp} \Rightarrow \vec{\mathbf{B}}_{\perp} = \frac{\vec{\mathbf{k}}}{\omega} \times \vec{\mathbf{E}} \quad (20)$$

Propagating wave in short

- \vec{E}_{\parallel} and \vec{B}_{\parallel} are constants in space and time, hence not interesting for wave propagation
- \vec{E}_{\perp} and \vec{B}_{\perp} can have $e^{i(\vec{k}\cdot\vec{r}-\omega t)}$ dependence, with $\vec{B}_{\perp} = (\vec{k}/\omega) \times \vec{E}$
- \vec{E} and \vec{B} fields are transverse to the direction of motion, and also orthogonal to each other.

Propagating wave in short

- $\vec{\mathbf{E}}_{\parallel}$ and $\vec{\mathbf{B}}_{\parallel}$ are constants in space and time, hence not interesting for wave propagation
- $\vec{\mathbf{E}}_{\perp}$ and $\vec{\mathbf{B}}_{\perp}$ can have $e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)}$ dependence, with $\vec{\mathbf{B}}_{\perp} = (\vec{\mathbf{k}}/\omega) \times \vec{\mathbf{E}}$
- $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$ fields are transverse to the direction of motion, and also orthogonal to each other.

Propagating wave in short

- $\vec{\mathbf{E}}_{\parallel}$ and $\vec{\mathbf{B}}_{\parallel}$ are constants in space and time, hence not interesting for wave propagation
- $\vec{\mathbf{E}}_{\perp}$ and $\vec{\mathbf{B}}_{\perp}$ can have $e^{i(\vec{\mathbf{k}} \cdot \vec{\mathbf{r}} - \omega t)}$ dependence, with $\vec{\mathbf{B}}_{\perp} = (\vec{\mathbf{k}}/\omega) \times \vec{\mathbf{E}}$
- $\vec{\mathbf{E}}$ and $\vec{\mathbf{B}}$ fields are transverse to the direction of motion, and also orthogonal to each other.

- 1 Relaxation to a stationary state
- 2 **Electromagnetic waves**
 - Propagating plane wave
 - **Decaying plane wave**
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

Decaying plane wave

- When $\omega\tau \ll 1$, **conduction current** dominates over displacement current

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (21)$$

- The solution of the form $\vec{\mathbf{E}}_0 e^{\pm i(kx - \omega t)}$ implies

$$k^2 = i\omega\mu\sigma = \omega\mu\sigma e^{i\pi/2} \quad (22)$$

$$\Rightarrow k = \sqrt{\omega\mu\sigma} e^{i\pi/4} = \sqrt{\omega\mu\sigma} \left(\frac{1+i}{\sqrt{2}} \right) \quad (23)$$

- This gives

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{\pm i(\text{Re}(k)x - \omega t)} e^{-\text{Im}(k)x} \quad (24)$$

- The wave then decays with a $e^{-\text{Im}(k)x}$ dependence inside the conducting medium.

Decaying plane wave

- When $\omega\tau \ll 1$, **conduction current** dominates over **displacement current**

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (21)$$

- The solution of the form $\vec{\mathbf{E}}_0 e^{\pm i(kx - \omega t)}$ implies

$$k^2 = i\omega\mu\sigma = \omega\mu\sigma e^{i\pi/2} \quad (22)$$

$$\Rightarrow k = \sqrt{\omega\mu\sigma} e^{i\pi/4} = \sqrt{\omega\mu\sigma} \left(\frac{1+i}{\sqrt{2}} \right) \quad (23)$$

- This gives

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{\pm i(\text{Re}(k)x - \omega t)} e^{-\text{Im}(k)x} \quad (24)$$

- The wave then decays with a $e^{-\text{Im}(k)x}$ dependence inside the conducting medium.

Decaying plane wave

- When $\omega\tau \ll 1$, **conduction current** dominates over **displacement current**

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (21)$$

- The solution of the form $\vec{\mathbf{E}}_0 e^{\pm i(kx - \omega t)}$ implies

$$k^2 = i\omega\mu\sigma = \omega\mu\sigma e^{i\pi/2} \quad (22)$$

$$\Rightarrow k = \sqrt{\omega\mu\sigma} e^{i\pi/4} = \sqrt{\omega\mu\sigma} \left(\frac{1+i}{\sqrt{2}} \right) \quad (23)$$

- This gives

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{\pm i(\text{Re}(k)x - \omega t)} e^{-\text{Im}(k)x} \quad (24)$$

- The wave then decays with a $e^{-\text{Im}(k)x}$ dependence inside the conducting medium.

Decaying plane wave

- When $\omega\tau \ll 1$, conduction current dominates over displacement current

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (21)$$

- The solution of the form $\vec{\mathbf{E}}_0 e^{\pm i(kx - \omega t)}$ implies

$$k^2 = i\omega\mu\sigma = \omega\mu\sigma e^{i\pi/2} \quad (22)$$

$$\Rightarrow k = \sqrt{\omega\mu\sigma} e^{i\pi/4} = \sqrt{\omega\mu\sigma} \left(\frac{1+i}{\sqrt{2}} \right) \quad (23)$$

- This gives

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{\pm i(\text{Re}(k)x - \omega t)} e^{-\text{Im}(k)x} \quad (24)$$

- The wave then decays with a $e^{-\text{Im}(k)x}$ dependence inside the conducting medium.

Decaying plane wave

- When $\omega\tau \ll 1$, conduction current dominates over displacement current

$$\nabla^2 \vec{\mathbf{E}} + \mu\epsilon\omega^2 \vec{\mathbf{E}} + i\omega\mu\sigma \vec{\mathbf{E}} = 0 \quad (21)$$

- The solution of the form $\vec{\mathbf{E}}_0 e^{\pm i(kx - \omega t)}$ implies

$$k^2 = i\omega\mu\sigma = \omega\mu\sigma e^{i\pi/2} \quad (22)$$

$$\Rightarrow k = \sqrt{\omega\mu\sigma} e^{i\pi/4} = \sqrt{\omega\mu\sigma} \left(\frac{1+i}{\sqrt{2}} \right) \quad (23)$$

- This gives

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{\pm i(\text{Re}(k)x - \omega t)} e^{-\text{Im}(k)x} \quad (24)$$

- The wave then decays with a $e^{-\text{Im}(k)x}$ dependence inside the conducting medium.

Skin depth in metals

- For metals, $\tau \sim 10^{-14}$ sec. So for $\omega \lesssim 10^{14}$ /s, conduction current dominates.
- A wave incident on a metallic surface will decay as

$$|\vec{E}| = |\vec{E}_0|e^{-r/\delta} \quad (25)$$

where, from the last page,

$$\delta = \sqrt{\frac{2}{\omega\mu\sigma}} = \sqrt{\frac{2c^2\tau}{\omega}} \quad (26)$$

- Within a distance δ from the surface of the metal, the wave would decrease in magnitude by a factor $1/e$. This δ is the “skin depth” of the metal. The surface currents will flow within this width.
- “Ideal” conductor $\Rightarrow \delta \rightarrow 0$.

Skin depth in metals

- For metals, $\tau \sim 10^{-14}$ sec. So for $\omega \lesssim 10^{14}$ /s, conduction current dominates.
- A wave incident on a metallic surface will decay as

$$|\vec{\mathbf{E}}| = |\vec{\mathbf{E}}_0|e^{-r/\delta} \quad (25)$$

where, from the last page,

$$\delta = \sqrt{\frac{2}{\omega\mu\sigma}} = \sqrt{\frac{2c^2\tau}{\omega}} \quad (26)$$

- Within a distance δ from the surface of the metal, the wave would decrease in magnitude by a factor $1/e$. This δ is the “skin depth” of the metal. The surface currents will flow within this width.
- “Ideal” conductor $\Rightarrow \delta \rightarrow 0$.

Skin depth in metals

- For metals, $\tau \sim 10^{-14}$ sec. So for $\omega \lesssim 10^{14}$ /s, conduction current dominates.
- A wave incident on a metallic surface will decay as

$$|\vec{E}| = |\vec{E}_0|e^{-r/\delta} \quad (25)$$

where, from the last page,

$$\delta = \sqrt{\frac{2}{\omega\mu\sigma}} = \sqrt{\frac{2c^2\tau}{\omega}} \quad (26)$$

- Within a distance δ from the surface of the metal, the wave would decrease in magnitude by a factor $1/e$. This δ is the “skin depth” of the metal. The surface currents will flow within this width.
- “Ideal” conductor $\Rightarrow \delta \rightarrow 0$.

Skin depth in metals

- For metals, $\tau \sim 10^{-14}$ sec. So for $\omega \lesssim 10^{14}$ /s, conduction current dominates.
- A wave incident on a metallic surface will decay as

$$|\vec{E}| = |\vec{E}_0|e^{-r/\delta} \quad (25)$$

where, from the last page,

$$\delta = \sqrt{\frac{2}{\omega\mu\sigma}} = \sqrt{\frac{2c^2\tau}{\omega}} \quad (26)$$

- Within a distance δ from the surface of the metal, the wave would decrease in magnitude by a factor $1/e$. This δ is the “skin depth” of the metal. The surface currents will flow within this width.
- “Ideal” conductor $\Rightarrow \delta \rightarrow 0$.

- 1 Relaxation to a stationary state
- 2 Electromagnetic waves
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

- 1 Relaxation to a stationary state
- 2 Electromagnetic waves
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

Work done for creating a charge distribution

- Work done in increasing charge density by $\delta\rho(\vec{\mathbf{x}})$:

$$\delta W = \int \phi(\vec{\mathbf{x}}) \delta\rho(\vec{\mathbf{x}}) dV = \epsilon_0 \int \phi(\vec{\mathbf{x}}) \delta(\nabla \cdot \vec{\mathbf{E}}) dV \quad (27)$$

- Integrate by parts:

$$\begin{aligned} \delta W &= \epsilon_0 \int \nabla \cdot (\phi \delta \vec{\mathbf{E}}) dV - \epsilon_0 \int (\nabla \phi) \cdot (\delta \vec{\mathbf{E}}) dV \\ \delta W &= \epsilon_0 \int \vec{\mathbf{E}} \cdot \delta \vec{\mathbf{E}} dV \end{aligned} \quad (28)$$

Total energy stored in electric field

$$W = \frac{\epsilon_0}{2} \int \vec{\mathbf{E}}^2 dV \quad (29)$$

Work done for creating a charge distribution

- Work done in increasing charge density by $\delta\rho(\vec{\mathbf{x}})$:

$$\delta W = \int \phi(\vec{\mathbf{x}}) \delta\rho(\vec{\mathbf{x}}) dV = \epsilon_0 \int \phi(\vec{\mathbf{x}}) \delta(\nabla \cdot \vec{\mathbf{E}}) dV \quad (27)$$

- Integrate by parts:

$$\begin{aligned} \delta W &= \epsilon_0 \int \nabla \cdot (\phi \delta \vec{\mathbf{E}}) dV - \epsilon_0 \int (\nabla \phi) \cdot (\delta \vec{\mathbf{E}}) dV \\ \delta W &= \epsilon_0 \int \vec{\mathbf{E}} \cdot \delta \vec{\mathbf{E}} dV \end{aligned} \quad (28)$$

Total energy stored in electric field

$$W = \frac{\epsilon_0}{2} \int \vec{\mathbf{E}}^2 dV \quad (29)$$

Work done for creating a charge distribution

- Work done in increasing charge density by $\delta\rho(\vec{\mathbf{x}})$:

$$\delta W = \int \phi(\vec{\mathbf{x}}) \delta\rho(\vec{\mathbf{x}}) dV = \epsilon_0 \int \phi(\vec{\mathbf{x}}) \delta(\nabla \cdot \vec{\mathbf{E}}) dV \quad (27)$$

- Integrate by parts:

$$\begin{aligned} \delta W &= \epsilon_0 \int \nabla \cdot (\phi \delta \vec{\mathbf{E}}) dV - \epsilon_0 \int (\nabla \phi) \cdot (\delta \vec{\mathbf{E}}) dV \\ \delta W &= \epsilon_0 \int \vec{\mathbf{E}} \cdot \delta \vec{\mathbf{E}} dV \end{aligned} \quad (28)$$

Total energy stored in electric field

$$W = \frac{\epsilon_0}{2} \int \vec{\mathbf{E}}^2 dV \quad (29)$$

Energy in a static magnetic field

- Just like a small incremental charge gives rise to $\delta q \rightarrow \delta \vec{E}$ against which δW needs to be done to bring incremental charge (that is stored in the resultant \vec{E}),

- A small incremental current gives rise to $\delta_t \vec{J} \rightarrow \delta_t (\nabla \times \vec{H}) \rightarrow \delta_t \vec{H} \rightarrow \delta_t (\nabla \times \vec{E}) \rightarrow \delta_t \vec{E}$
($\delta_t \Rightarrow$ small change with time)

δW needs to be done against this “back emf” to produce incremental current (that will be stored in the resultant \vec{B}).

- The energy stored in the magnetic field during time δt :
$$\delta U_m = -\delta_t \vec{E} \cdot \vec{J} \delta t dV$$

Energy in a static magnetic field

- Just like a small incremental charge gives rise to $\delta q \rightarrow \delta \vec{E}$ against which δW needs to be done to bring incremental charge (that is stored in the resultant \vec{E}),
- A small incremental current gives rise to $\delta_t \vec{J} \rightarrow \delta_t (\nabla \times \vec{H}) \rightarrow \delta_t \vec{H} \rightarrow \delta_t (\nabla \times \vec{E}) \rightarrow \delta_t \vec{E}$
($\delta_t \Rightarrow$ small change with time)
 δW needs to be done against this “back emf” to produce incremental current (that will be stored in the resultant \vec{B}).
- The energy stored in the magnetic field during time δt :
 $\delta U_m = -\delta_t \vec{E} \cdot \vec{J} \delta t dV$

Energy in a static magnetic field

- Just like a small incremental charge gives rise to $\delta q \rightarrow \delta \vec{E}$ against which δW needs to be done to bring incremental charge (that is stored in the resultant \vec{E}),
- A small incremental current gives rise to $\delta_t \vec{J} \rightarrow \delta_t (\nabla \times \vec{H}) \rightarrow \delta_t \vec{H} \rightarrow \delta_t (\nabla \times \vec{E}) \rightarrow \delta_t \vec{E}$
($\delta_t \Rightarrow$ small change with time)
 δW needs to be done against this “back emf” to produce incremental current (that will be stored in the resultant \vec{B}).
- The energy stored in the magnetic field during time δt :
$$\delta U_m = -\delta_t \vec{E} \cdot \vec{J} \delta t dV$$

Energy stored in static magnetic field

- Energy stored in magnetic field during time δt :

$$\delta U_m = - \int \delta_t \vec{\mathbf{E}} \cdot \vec{\mathbf{J}} dV \delta t = - \int \delta_t \vec{\mathbf{E}} \cdot (\nabla \times \vec{\mathbf{H}}) dV \delta t \quad (30)$$

$$= - \int \vec{\mathbf{H}} \cdot (\nabla \times \delta_t \vec{\mathbf{E}}) dV \delta t + \int \nabla \cdot (\delta_t \vec{\mathbf{E}} \times \vec{\mathbf{H}}) dV \delta t$$

$$= \int \vec{\mathbf{H}} \cdot \frac{\partial(\delta_t \vec{\mathbf{B}})}{\partial t} dV \delta t \quad (31)$$

- Incremental energy stored: $\delta U_m = \int \vec{\mathbf{H}} \cdot \delta \vec{\mathbf{B}} dV$

Total energy stored in magnetic field (μ constant)

$$W = \frac{1}{2\mu} \int \vec{\mathbf{B}}^2 dV \quad (32)$$

Energy stored in static magnetic field

- Energy stored in magnetic field during time δt :

$$\delta U_m = - \int \delta_t \vec{\mathbf{E}} \cdot \vec{\mathbf{J}} dV \delta t = - \int \delta_t \vec{\mathbf{E}} \cdot (\nabla \times \vec{\mathbf{H}}) dV \delta t \quad (30)$$

$$= - \int \vec{\mathbf{H}} \cdot (\nabla \times \delta_t \vec{\mathbf{E}}) dV \delta t + \int \nabla \cdot (\delta_t \vec{\mathbf{E}} \times \vec{\mathbf{H}}) dV \delta t$$

$$= \int \vec{\mathbf{H}} \cdot \frac{\partial(\delta_t \vec{\mathbf{B}})}{\partial t} dV \delta t \quad (31)$$

- Incremental energy stored: $\delta U_m = \int \vec{\mathbf{H}} \cdot \delta \vec{\mathbf{B}} dV$

Total energy stored in magnetic field (μ constant)

$$W = \frac{1}{2\mu} \int \vec{\mathbf{B}}^2 dV \quad (32)$$

A note about $\vec{\mathbf{E}} \times \vec{\mathbf{H}}$

- We neglected the term $\int \nabla \cdot (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) dV = \oint (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) \cdot d\vec{\mathbf{S}}$
- This is indeed valid for static electromagnetic fields
- But for time-dependent fields, we shall see later that the leading terms in $\vec{\mathbf{E}}$ and $\vec{\mathbf{H}}$ go as $1/r$, so over the surface of a sphere with large radius r , the integral actually will have a constant nonzero value.
- This will be the energy radiated away at infinity due to the changing currents. $\vec{\mathbf{N}} \equiv \vec{\mathbf{E}} \times \vec{\mathbf{H}}$ will be defined as the **Poynting vector**, which gives the rate of loss of energy through radiation.

A note about $\vec{\mathbf{E}} \times \vec{\mathbf{H}}$

- We neglected the term $\int \nabla \cdot (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) dV = \oint (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) \cdot d\vec{\mathbf{S}}$
- This is indeed valid for static electromagnetic fields
- But for time-dependent fields, we shall see later that the leading terms in $\vec{\mathbf{E}}$ and $\vec{\mathbf{H}}$ go as $1/r$, so over the surface of a sphere with large radius r , the integral actually will have a constant nonzero value.
- This will be the energy radiated away at infinity due to the changing currents. $\vec{\mathbf{N}} \equiv \vec{\mathbf{E}} \times \vec{\mathbf{H}}$ will be defined as the **Poynting vector**, which gives the rate of loss of energy through radiation.

A note about $\vec{\mathbf{E}} \times \vec{\mathbf{H}}$

- We neglected the term $\int \nabla \cdot (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) dV = \oint (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) \cdot d\vec{\mathbf{S}}$
- This is indeed valid for static electromagnetic fields
- But for time-dependent fields, we shall see later that the leading terms in $\vec{\mathbf{E}}$ and $\vec{\mathbf{H}}$ go as $1/r$, so over the surface of a sphere with large radius r , the integral actually will have a constant nonzero value.
- This will be the energy radiated away at infinity due to the changing currents. $\vec{\mathbf{N}} \equiv \vec{\mathbf{E}} \times \vec{\mathbf{H}}$ will be defined as the **Poynting vector**, which gives the rate of loss of energy through radiation.

A note about $\vec{\mathbf{E}} \times \vec{\mathbf{H}}$

- We neglected the term $\int \nabla \cdot (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) dV = \oint (\vec{\mathbf{E}} \times \vec{\mathbf{H}}) \cdot d\vec{\mathbf{S}}$
- This is indeed valid for static electromagnetic fields
- But for time-dependent fields, we shall see later that the leading terms in $\vec{\mathbf{E}}$ and $\vec{\mathbf{H}}$ go as $1/r$, so over the surface of a sphere with large radius r , the integral actually will have a constant nonzero value.
- This will be the energy radiated away at infinity due to the changing currents. $\vec{\mathbf{N}} \equiv \vec{\mathbf{E}} \times \vec{\mathbf{H}}$ will be defined as the **Poynting vector**, which gives the rate of loss of energy through radiation.

- 1 Relaxation to a stationary state
- 2 Electromagnetic waves
 - Propagating plane wave
 - Decaying plane wave
- 3 Energy of EM fields
 - Energy in static electric / magnetic fields
 - Energy in EM waves

Quadratic quantities and factors of 2

- In Electrodynamics, for convenience, we often use notation involving complex numbers (mainly exponentials), e.g.

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{i(kx - \omega t)}, \quad \vec{\mathbf{B}} = -i\vec{\mathbf{B}}_0 e^{i(kx - \omega t)} \quad (33)$$

when we actually want to represent

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 \cos(kx - \omega t) = \text{Re}(\vec{\mathbf{E}}_0 e^{i(kx - \omega t)}) \quad (34)$$

$$\vec{\mathbf{B}} = \vec{\mathbf{B}}_0 \sin(kx - \omega t) = \text{Re}(i\vec{\mathbf{B}}_0 e^{i(kx - \omega t)}) \quad (35)$$

- While performing calculations in complex notation and taking the real part of the final answer works as long as we are dealing with quantities linear in $\vec{\mathbf{E}}$ or $\vec{\mathbf{B}}$, one has to be careful while dealing with quadratic (or higher order) quantities.
- For example, in the complex notation above,

$$\langle |\vec{\mathbf{E}}|^2 \rangle = \langle |\vec{\mathbf{E}}^* \cdot \vec{\mathbf{E}}| \rangle = |\vec{\mathbf{E}}_0|^2 \quad (36)$$

while the actual answer should be (using real notation)

$$\langle |\vec{\mathbf{E}}|^2 \rangle = |\vec{\mathbf{E}}_0|^2 \langle \cos^2(kx - \omega t) \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0|^2 \quad (37)$$

Quadratic quantities and factors of 2

- In Electrodynamics, for convenience, we often use notation involving complex numbers (mainly exponentials), e.g.

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{i(kx - \omega t)}, \quad \vec{\mathbf{B}} = -i\vec{\mathbf{B}}_0 e^{i(kx - \omega t)} \quad (33)$$

when we actually want to represent

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 \cos(kx - \omega t) = \text{Re}(\vec{\mathbf{E}}_0 e^{i(kx - \omega t)}) \quad (34)$$

$$\vec{\mathbf{B}} = \vec{\mathbf{B}}_0 \sin(kx - \omega t) = \text{Re}(i\vec{\mathbf{B}}_0 e^{i(kx - \omega t)}) \quad (35)$$

- While performing calculations in complex notation and taking the real part of the final answer works as long as we are dealing with quantities linear in $\vec{\mathbf{E}}$ or $\vec{\mathbf{B}}$, one has to be careful while dealing with quadratic (or higher order) quantities.
- For example, in the complex notation above,

$$\langle |\vec{\mathbf{E}}|^2 \rangle = \langle |\vec{\mathbf{E}}^* \cdot \vec{\mathbf{E}}| \rangle = |\vec{\mathbf{E}}_0|^2 \quad (36)$$

while the actual answer should be (using real notation)

$$\langle |\vec{\mathbf{E}}|^2 \rangle = |\vec{\mathbf{E}}_0|^2 \langle \cos^2(kx - \omega t) \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0|^2 \quad (37)$$

Quadratic quantities and factors of 2

- In Electrodynamics, for convenience, we often use notation involving complex numbers (mainly exponentials), e.g.

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 e^{i(kx - \omega t)}, \quad \vec{\mathbf{B}} = -i\vec{\mathbf{B}}_0 e^{i(kx - \omega t)} \quad (33)$$

when we actually want to represent

$$\vec{\mathbf{E}} = \vec{\mathbf{E}}_0 \cos(kx - \omega t) = \text{Re}(\vec{\mathbf{E}}_0 e^{i(kx - \omega t)}) \quad (34)$$

$$\vec{\mathbf{B}} = \vec{\mathbf{B}}_0 \sin(kx - \omega t) = \text{Re}(i\vec{\mathbf{B}}_0 e^{i(kx - \omega t)}) \quad (35)$$

- While performing calculations in complex notation and taking the real part of the final answer works as long as we are dealing with quantities linear in $\vec{\mathbf{E}}$ or $\vec{\mathbf{B}}$, one has to be careful while dealing with quadratic (or higher order) quantities.
- For example, in the complex notation above,

$$\langle |\vec{\mathbf{E}}|^2 \rangle = \langle |\vec{\mathbf{E}}^* \cdot \vec{\mathbf{E}}| \rangle = |\vec{\mathbf{E}}_0|^2 \quad (36)$$

while the actual answer should be (using real notation)

$$\langle |\vec{\mathbf{E}}|^2 \rangle = |\vec{\mathbf{E}}_0|^2 \langle \cos^2(kx - \omega t) \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0|^2 \quad (37)$$

Energy density stored in EM wave

- We have already seen that the energy stored in electric field is $U_e = (1/2)\epsilon_0|\vec{\mathbf{E}}|^2$ (we showed this result for a static field). When the electric field represents a propagating wave, then taking into account the “factor of 2” for averaged quadratic quantities, we get

$$\langle U_e \rangle = \frac{1}{4}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (38)$$

- The energy stored in magnetic field is $U_m = (1/2)|\vec{\mathbf{B}}|^2/\mu_0$ (we showed it for a static magnetic field). For a propagating wave, $|\vec{\mathbf{B}}| = |\vec{\mathbf{k}}/\omega||\vec{\mathbf{E}}|$. Including the “factor of 2”, we get

$$\langle U_m \rangle = \frac{1}{4} \frac{|\vec{\mathbf{B}}_0|^2}{\mu_0} = \frac{1}{4} \frac{|\vec{\mathbf{k}}|^2}{\omega^2 \mu_0} |\vec{\mathbf{E}}_0|^2 = \frac{1}{4}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (39)$$

- For a plane EM wave, energy stored in electric and magnetic field is equal. The total energy of an EM wave is

$$\langle U \rangle = \langle U_e \rangle + \langle U_m \rangle = \frac{1}{2}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (40)$$

Energy density stored in EM wave

- We have already seen that the energy stored in electric field is $U_e = (1/2)\epsilon_0|\vec{\mathbf{E}}|^2$ (we showed this result for a static field). When the electric field represents a propagating wave, then taking into account the “factor of 2” for averaged quadratic quantities, we get

$$\langle U_e \rangle = \frac{1}{4}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (38)$$

- The energy stored in magnetic field is $U_m = (1/2)|\vec{\mathbf{B}}|^2/\mu_0$ (we showed it for a static magnetic field). For a propagating wave, $|\vec{\mathbf{B}}| = |\vec{\mathbf{k}}/\omega||\vec{\mathbf{E}}|$. Including the “factor of 2”, we get

$$\langle U_m \rangle = \frac{1}{4} \frac{|\vec{\mathbf{B}}_0|^2}{\mu_0} = \frac{1}{4} \frac{|\vec{\mathbf{k}}|^2}{\omega^2 \mu_0} |\vec{\mathbf{E}}_0|^2 = \frac{1}{4}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (39)$$

- For a plane EM wave, energy stored in electric and magnetic field is equal. The total energy of an EM wave is

$$\langle U \rangle = \langle U_e \rangle + \langle U_m \rangle = \frac{1}{2}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (40)$$

Energy density stored in EM wave

- We have already seen that the energy stored in electric field is $U_e = (1/2)\epsilon_0|\vec{\mathbf{E}}|^2$ (we showed this result for a static field). When the electric field represents a propagating wave, then taking into account the “factor of 2” for averaged quadratic quantities, we get

$$\langle U_e \rangle = \frac{1}{4}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (38)$$

- The energy stored in magnetic field is $U_m = (1/2)|\vec{\mathbf{B}}|^2/\mu_0$ (we showed it for a static magnetic field). For a propagating wave, $|\vec{\mathbf{B}}| = |\vec{\mathbf{k}}/\omega||\vec{\mathbf{E}}|$. Including the “factor of 2”, we get

$$\langle U_m \rangle = \frac{1}{4} \frac{|\vec{\mathbf{B}}_0|^2}{\mu_0} = \frac{1}{4} \frac{|\vec{\mathbf{k}}|^2}{\omega^2 \mu_0} |\vec{\mathbf{E}}_0|^2 = \frac{1}{4}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (39)$$

- For a plane EM wave, energy stored in electric and magnetic field is equal. The total energy of an EM wave is

$$\langle U \rangle = \langle U_e \rangle + \langle U_m \rangle = \frac{1}{2}\epsilon_0|\vec{\mathbf{E}}_0|^2 \quad (40)$$

Energy transported by the EM fields

- The rate of energy transport is given by the Poynting vector,

$$\vec{\mathbf{N}} = \vec{\mathbf{E}} \times \vec{\mathbf{H}} \quad (41)$$

- The time-averaged value of this quantity is

$$\langle |\vec{\mathbf{N}}| \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0| \cdot |\vec{\mathbf{H}}_0| = \frac{1}{2} |\vec{\mathbf{E}}_0| \frac{|\vec{\mathbf{k}}|}{\omega \mu} |\vec{\mathbf{E}}_0| = \frac{1}{2} \sqrt{\frac{\epsilon_0}{\mu_0}} |\vec{\mathbf{E}}_0|^2 \quad (42)$$

- Compared with the rate of energy consumption in a conductor, $(1/2)\sigma |\vec{\mathbf{E}}_0|^2$, the quantity $\sqrt{\epsilon_0/\mu_0}$ is termed the **conductance of vacuum**
- Similarly, $\sqrt{\epsilon/\mu}$ is the **conductance of a medium through which an EM wave propagates**
- Note that $\langle |\vec{\mathbf{N}}| \rangle = c \langle U \rangle$, since the wave transports energy at the speed c .

Energy transported by the EM fields

- The rate of energy transport is given by the Poynting vector,

$$\vec{\mathbf{N}} = \vec{\mathbf{E}} \times \vec{\mathbf{H}} \quad (41)$$

- The time-averaged value of this quantity is

$$\langle |\vec{\mathbf{N}}| \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0| \cdot |\vec{\mathbf{H}}_0| = \frac{1}{2} |\vec{\mathbf{E}}_0| \frac{|\vec{\mathbf{k}}|}{\omega \mu} |\vec{\mathbf{E}}_0| = \frac{1}{2} \sqrt{\frac{\epsilon_0}{\mu_0}} |\vec{\mathbf{E}}_0|^2 \quad (42)$$

- Compared with the rate of energy consumption in a conductor, $(1/2)\sigma |\vec{\mathbf{E}}_0|^2$, the quantity $\sqrt{\epsilon_0/\mu_0}$ is termed the **conductance of vacuum**
- Similarly, $\sqrt{\epsilon/\mu}$ is the **conductance of a medium through which an EM wave propagates**
- Note that $\langle |\vec{\mathbf{N}}| \rangle = c \langle U \rangle$, since the wave transports energy at the speed c .

Energy transported by the EM fields

- The rate of energy transport is given by the Poynting vector,

$$\vec{\mathbf{N}} = \vec{\mathbf{E}} \times \vec{\mathbf{H}} \quad (41)$$

- The time-averaged value of this quantity is

$$\langle |\vec{\mathbf{N}}| \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0| \cdot |\vec{\mathbf{H}}_0| = \frac{1}{2} |\vec{\mathbf{E}}_0| \frac{|\vec{\mathbf{k}}|}{\omega \mu} |\vec{\mathbf{E}}_0| = \frac{1}{2} \sqrt{\frac{\epsilon_0}{\mu_0}} |\vec{\mathbf{E}}_0|^2 \quad (42)$$

- Compared with the rate of energy consumption in a conductor, $(1/2)\sigma |\vec{\mathbf{E}}_0|^2$, the quantity $\sqrt{\epsilon_0/\mu_0}$ is termed the **conductance of vacuum**
- Similarly, $\sqrt{\epsilon/\mu}$ is the **conductance of a medium through which an EM wave propagates**
- Note that $\langle |\vec{\mathbf{N}}| \rangle = c \langle U \rangle$, since the wave transports energy at the speed c .

Energy transported by the EM fields

- The rate of energy transport is given by the Poynting vector,

$$\vec{\mathbf{N}} = \vec{\mathbf{E}} \times \vec{\mathbf{H}} \quad (41)$$

- The time-averaged value of this quantity is

$$\langle |\vec{\mathbf{N}}| \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0| \cdot |\vec{\mathbf{H}}_0| = \frac{1}{2} |\vec{\mathbf{E}}_0| \frac{|\vec{\mathbf{k}}|}{\omega \mu} |\vec{\mathbf{E}}_0| = \frac{1}{2} \sqrt{\frac{\epsilon_0}{\mu_0}} |\vec{\mathbf{E}}_0|^2 \quad (42)$$

- Compared with the rate of energy consumption in a conductor, $(1/2)\sigma |\vec{\mathbf{E}}_0|^2$, the quantity $\sqrt{\epsilon_0/\mu_0}$ is termed the **conductance of vacuum**
- Similarly, $\sqrt{\epsilon/\mu}$ is the **conductance of a medium through which an EM wave propagates**
- Note that $\langle |\vec{\mathbf{N}}| \rangle = c \langle U \rangle$, since the wave transports energy at the speed c .

Energy transported by the EM fields

- The rate of energy transport is given by the Poynting vector,

$$\vec{\mathbf{N}} = \vec{\mathbf{E}} \times \vec{\mathbf{H}} \quad (41)$$

- The time-averaged value of this quantity is

$$\langle |\vec{\mathbf{N}}| \rangle = \frac{1}{2} |\vec{\mathbf{E}}_0| \cdot |\vec{\mathbf{H}}_0| = \frac{1}{2} |\vec{\mathbf{E}}_0| \frac{|\vec{\mathbf{k}}|}{\omega \mu} |\vec{\mathbf{E}}_0| = \frac{1}{2} \sqrt{\frac{\epsilon_0}{\mu_0}} |\vec{\mathbf{E}}_0|^2 \quad (42)$$

- Compared with the rate of energy consumption in a conductor, $(1/2)\sigma |\vec{\mathbf{E}}_0|^2$, the quantity $\sqrt{\epsilon_0/\mu_0}$ is termed the **conductance of vacuum**
- Similarly, $\sqrt{\epsilon/\mu}$ is the **conductance of a medium through which an EM wave propagates**
- Note that $\langle |\vec{\mathbf{N}}| \rangle = c \langle U \rangle$, since the wave transports energy at the speed c .

Recap of topics covered in this lecture

- Relaxation to stationary state, relaxation time
- Electromagnetic wave: displacement and conduction current
- Transverse EM field solutions for a propagating wave
- Decay of EM waves in a conductor, skin depth
- Energy stored in EM fields
- Energy transported by an EM wave